

NetBackup™ Access Appliance 8.6 Troubleshooting Guide

Access Appliance Troubleshooting Guide

Last updated: 2026-04-13

Legal Notice

Copyright © 2026 Cohesity All rights reserved.

© 2026 Cohesity All Rights Reserved. Veritas, the Veritas Logo and other Veritas Marks are trademarks of Cohesity in the US and/or internationally. The information supplied herein is the confidential and proprietary information of Veritas and may only be used (a) by the intended recipients and (b) in conjunction with validly licensed Veritas software and services. Find the terms of Veritas licenses at www.cohesity.com/agreements.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. COHESITY SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

Cohesity Support

Reach Cohesity Support

There are several ways to create a Cohesity support case.

- Go to [Cohesity Support](#), to search in our knowledge base; or contact us by phone - United States and Canada: 1-855-9CO-HESI (926-4374), option 2.
- Log in to the [Cohesity Support Portal](#) to create a new case.
- Click the (?) icon on the Cohesity UI and select Support Portal.

Support/Service Assistance

First, contact the Service Provider that you have contracted for service and support. If you work directly with Cohesity and have a product warranty/entitlement, repair pricing, or technical support-related question, see your options below:

- To find solutions to your product issues or for suggestions or best practices, visit the [Cohesity Knowledge Base](#).
- Log in to the [Cohesity Support Portal](#) to create a new case.
- To monitor your open cases, log in to the portal and click the **Cases** tab on the home page. This page should have all the case statuses and updates. You can also view individual case status.

Cohesity Software Running on Partner Hardware

For Cohesity software running on qualified third-party hardware, the following support workflow applies:

1. The customer may contact Cohesity Support first if the issue cannot be determined as a hardware issue.

Note: Cohesity cannot process hardware replacement requests for partner hardware.

2. Cohesity Support triages the issue. If it is a software issue, Cohesity Support continues to work on it.
3. If it is a hardware/firmware issue or is suspected to be a hardware/firmware issue, Cohesity provides information about the issue to the customer and requests that the customer open a support ticket with the appropriate partner.
4. If needed, Cohesity Support can join a three-way call with the partner and the customer.
5. The customer informs Cohesity Support on the progress of the partner's case.

Contents

Chapter 1	Introduction	6
	About troubleshooting	6
	General tips for the troubleshooting process	6
	General techniques for the troubleshooting process	7
Chapter 2	General troubleshooting procedures	8
	About general troubleshooting procedures	8
	Viewing the Access Appliance log files	8
	About event logs	10
	Setting the NetBackup client log levels and debugging options	10
	Retrieving and sending debugging information	11
	Collecting time-based and archived logs	15
	Collecting logs for cluster nodes	18
Chapter 3	Monitoring Access Appliance	19
	About monitoring Access Appliance operations	19
	Monitoring hardware components	19
Chapter 4	Common recovery procedures	21
	About common recovery procedures	21
	Restarting servers	22
	Restarting cluster services	22
	Bringing services online	23
	Using the services command	23
	Recovering from a non-graceful shutdown	24
	Testing the network connectivity	25
	Troubleshooting with traceroute	26
	Using the traceroute command	26
	Collecting the metasave image of a file system	27
	Replacing an Ethernet interface card (online mode)	28
	Replacing an Access Appliance node	31
	Uninstalling a patch release or software upgrade	32

Chapter 5	Troubleshooting Access Appliance installation and configuration issues	33
	How to find the management console IP	33
	Viewing the installation logs	34
	Installation fails and does not complete	35
Chapter 6	Troubleshooting Access Appliance GUI startup issues	36
	Resolving GUI startup issues	36
Chapter 7	Troubleshooting Veritas Data Deduplication issues	39
	Log locations for the Veritas Data Deduplication server	39
Index		40

Introduction

This chapter includes the following topics:

- [About troubleshooting](#)
- [General tips for the troubleshooting process](#)
- [General techniques for the troubleshooting process](#)

About troubleshooting

Troubleshooting procedures for Access Appliance include the following types of procedures:

- Alert and log message review
- Routine maintenance tasks
- Commonly used recovery procedures
- Feature-specific problems and resolutions

Each of these procedures are described in the remaining chapters of this guide.

Some of the troubleshooting procedures in this guide require that you log on as the `maintenance user`.

General tips for the troubleshooting process

To troubleshoot a problem, it helps to consider the following:

- Check for previous occurrence.
Check existing troubleshooting information to see if the problem has occurred before. For this type of information, a good source is the *Access Appliance Release Notes*. The release notes contain a list of known issues for Access Appliance and possible workarounds.

- Consider recent alterations.
If a system has problems immediately after some kind of maintenance, software upgrade, or other change, the problems might be linked to those changes.
- Determine what works.
If a system does not produce the desired end result, look for what operates properly. Identify where the problem is not and focus your efforts in other areas. Whatever components or subsystems necessary for the properly working parts to function are probably okay.
- Use your experience.
Based on your knowledge of how a system works, think of various failures that might cause this problem to occur. Check for those failures. Start with the most likely failures based on circumstances, history, or knowledge of existing feature weaknesses.

General techniques for the troubleshooting process

After applying some general troubleshooting tips to narrow the scope of a problem, here are some techniques to further isolate the problem:

- Divide the system into sections.
In a system with multiple sections or stages, carefully measure the variables going in and out of each stage until you find a stage where things do not look right. For example, if you run across a problem with a replication job, check to see if the job has run successfully before and try to determine the time frame when the job started to fail.
- Monitor system behavior over time (or location).
Display a list of services and their current status using the `Support> services showall` command.
Set up a process to monitor system activity over a period of time or to monitor system activity across the network. This monitoring is especially helpful to track down intermittent problems, processor activity problems, node connection problems, and so on.

General troubleshooting procedures

This chapter includes the following topics:

- [About general troubleshooting procedures](#)
- [Viewing the Access Appliance log files](#)
- [About event logs](#)
- [Setting the NetBackup client log levels and debugging options](#)
- [Retrieving and sending debugging information](#)
- [Collecting time-based and archived logs](#)
- [Collecting logs for cluster nodes](#)

About general troubleshooting procedures

This chapter provides an overview of general troubleshooting procedures you can use to help discover and fix problems.

Viewing the Access Appliance log files

In addition to the Alerts panel on the Access Appliance dashboard, the Access Appliance `/opt/VRTSnas/log` directory is a good place to find out more about problems that may occur.

To view the Access Appliance log files when the appliance lockdown mode is not set

- 1 Use `support elevate` to log in with root privileges.
- 2 Navigate to the `/opt/VRTSnas/log` directory.

If your appliance is in lockdown mode, you need assistance from Veritas Support to access the log files.

To view the Access Appliance log files when the appliance lockdown mode is set

- 1 Log on to the node-level CLI on any node in the cluster.
- 2 Run the `show serial-number` command to get the serial number for a specific node.
- 3 If you have permission to generate access key on the SHI portal, then go to the portal to generate access key with the serial number that you got in step 2. For more information, refer to the *System Health Insights User Guide*.

If you do not have the permission to generate the access key on the SHI portal, open a ticket with Veritas Support to generate an access key. Mention the serial number in the Support case. The Veritas Support will generate an access key with the serial number provided. Set an access passphrase which will be required later to elevate to root.

- 4 Log on to the Access Appliance shell on the same node as in step 2.
- 5 When your representative asks you to, run the `support unlock` command. You are prompted to enter the maintenance password. Enter the maintenance password and press **Enter**. You are prompted to enter an access key. Enter the access key that you got in step 3. You are prompted to enter an access passphrase. Enter the access passphrase that you set in step 3. Press **Enter** to unlock the root shell access to the current node (all other nodes remain locked).
- 6 Run the `support elevate` command. Enter the maintenance password. You are prompted to enter an access passphrase. Enter the access passphrase set in step 3. Press **Enter** to get into the root shell.
- 7 To view the logs, navigate to the `/opt/VRTSnas/log` directory.
- 8 Run the `support lock` command on a specific node to lock that node. If no manual lock is issued, the node is locked automatically after 12 hours. All the current users are removed from the root shell in a single node.

Note: The access key expires in 2 hours.

About event logs

In addition to the system log, each Access Appliance feature has an associated event log. When a problem occurs, one of the quickest ways to learn more about what occurred is to examine these log files. Event logs for Access Appliance features are stored in the `/opt/VRTSnas/log` directory.

Note: You should not delete or alter log files while troubleshooting, as it may hamper further investigation by Veritas Technical Support.

To view the event logs:

- 1 Use SSH to log in to the node using admin privileges.
- 2 Type `support elevate` and when prompted enter the password for the maintenance account.
- 3 Navigate to the `/opt/VRTSnas/log` directory.

Event logs for Access Appliance features are stored in this directory.

Setting the NetBackup client log levels and debugging options

You can set NetBackup client log levels as well as different debugging options, and then upload the information to an external FTP or SCP server. You can use this debugging information to send to Veritas Technical Support.

See [“Retrieving and sending debugging information”](#) on page 11.

You can find NetBackup log information by using the `Backup> show` command. See the `backup_show(1)` man page.

You can see what NetBackup log levels and debugging options have been enabled by executing the `Backup> show` command.

See the *Veritas NetBackup Administrator's Guide, Volume 1* for more information on NetBackup logging.

Valid log level values range from 1 to 5, 5 being the most detailed. See the `support_debuginfo(1)` man page.

To set the NetBackup client log levels

- 1 Set the NetBackup database log level:

```
Support> debuginfo setlog nbu database loglevel
```

- 2 Set the NetBackup global debugging log level:

```
Support> debuginfo setlog nbu global loglevel
```

Global logging controls the logging level for the processes that are set in the **Logging** dialog box in the NetBackup Administration Console.

To set the NetBackup debugging options

- 1 Enable the NetBackup client to perform robust logging in the cluster.

```
Support> debuginfo setlog nbu enable robust
```

Robust logging limits the amount of disk space that a log directory consumes.

- 2 Enable the NetBackup client to perform critical process logging in the cluster.

```
Support> debuginfo setlog nbu enable critical
```

The enable critical process option lets you automatically log critical NetBackup processes. Log directories for the critical processes are created and logging begins when this option is enabled in the **Logging** host properties in the NetBackup Administration Console.

Retrieving and sending debugging information

You can retrieve Access Appliance debugging information from the Access Appliance node and send the information to a server using an external FTP or SCP server.

If a node is part of the cluster, you can use the Veritas Access CLI to run the `debuginfo` command to collect and upload debug information to an SCP or an FTP server. If the node is not a part of the Access cluster, the Veritas Access CLI is not accessible, and you must instead use the `collect_debuginfo.sh` script to collect and upload the debug information.

See the following article for more information on how to provide data for Veritas Technical Support:

<http://www.veritas.com/docs/000097935>

Uploading debug information from a cluster node

You can upload debugging information from a specified node to an external server.

```
Support> debuginfo upload nodename  
          debug-URL module
```

For example, to upload all debugging information to an FTP server:

```
Support> debuginfo upload node1_1  
ftp://admin@ftp.docserver.company.com/patches/ all
```

nodename Specifies the *nodename* from which to collect the debugging information.

debug-URL Specifies the remote file or directory for uploading debugging information.

Depending on the type of server from which you upload debugging information, use one of the following example URL formats:

```
ftp://admin@ftp.docserver.company.com/  
patches/
```

```
scp://root@server.company.com:/tmp/
```

If *debug-URL* specifies a remote file, the debuginfo file is saved by that name. If *debug-URL* specifies a remote directory, the debuginfo file name displays as the following:

```
nas_debuginfo_nodename_modulename_timestamp.tar.gz
```

module

Specifies the values for *module*.

The following options are supported:

- `generic`: This module collects generic information such as details about the operating system and SOS reports. This does not collect product information.
- `nas`: This module collects product information from the cluster nodes.
- `os`: This module collects SOS reports from all the cluster nodes.
- `explorer`: The VxExplorer utility collects logs and environment data from all the servers where the Access Appliance product is installed.
- `install`: This module collects the install logs from the CPI install log directory `/opt/VRTS/install/logs/`.
- `nas-procstacks`: This module collects the stack trace for all the daemons that are in running state.
- `netbackup`: This module collects logs about NetBackup from nodes.
- `appliance`: This module collects the logs related to the appliance.
- `sds`: This module collects SDS logs.
- `api_gateway`: This module collects API gateway logs.
- `upgrade`: This module collect the upgrade logs for all the cluster nodes.
- `backup`: This module collects NetBackup client logs and other diagnostic information.
- `vdd`: This module collects the deduplication logs provided dedupe is configured on the cluster nodes.
- `default`: This module collects logs from all modules of the cluster nodes except the `os` module.
- `all`: This module collects information for all the above modules from the cluster nodes.

The `Support> debuginfo` command also collects information for the `sosreport` command for Red Hat Enterprise Linux (RHEL). The `sosreport` is collected for all the loaded modules except for the `selinux` module.

Uploading debug information from a node that is not a part of the Access cluster

Use the `/opt/VRTSnas/scripts/support/collect_debuginfo.sh` script to collect and upload debug information when a node is not a part of the Access cluster. The script uses the following format:

```
/opt/VRTSnas/scripts/support/collect_debuginfo.sh -o upload -n  
nodename -d debug-URL -m module
```

where:

upload Specifies the operation to perform. Use the upload option to upload the debug information to the location specified by the *debug-URL* parameter.

nodename Specifies the name of the node from where you want to collect the debug information.

debug-URL Specifies the location for uploading the debug information. The location can be an SCP server, an FTP server, or a remote file or a directory. Use one of the following formats based on location where you want to upload the debug information:

```
ftp://url
```

For example:

```
ftp://admin@ftp.docserver.company.com/
```

```
scp://url
```

For example:

```
scp://root@server.company.com:/tmp/
```

If you specify a remote file, the debug information is saved in the specified file. If you specify a remote directory, the debug information is saved in the directory as a *tar.gz* file in the following format:

```
nas_debuginfo_nodename_modulename_timestamp.tar.gz.
```

For example:

The `sh /opt/VRTSnas/scripts/support/collect_debuginfo.sh -o upload -n node_01 -d file:///root/log/ -m nas-procstacks` uploads the information to the `nas_debuginfo_node_01_nas-procstacks_201808270145.tar.gz` file in the `/root/log` directory.

modules Specifies the modules.

The following options are supported:

- *generic*: This module collects generic information such as details about the operating system and SOS reports. This does not collect product information.
- *nas*: This module collects product information from the cluster nodes.
- *os*: This module collects SOS reports from all the cluster nodes.
- *explorer*: The VxExplorer utility collects logs and environment data from all the servers where the Access Appliance product is installed.
- *install*: This module collects the install logs from the CPI install log directory `/opt/VRTS/install/logs/`.
- *nas-procstacks*: This module collects the stack trace for all the daemons that are in running state.
- *netbackup* : This module collects logs about NetBackup from nodes.
- *appliance*: This module collects the logs related to the appliance.
- *sds*: This module collects SDS logs.
- *api_gateway*: This module collects API gateway logs.
- *upgrade*: This module collect the upgrade logs for all the cluster nodes.
- *backup*: This module collects NetBackup client logs and other diagnostic information.
- *vdd*: This module collects the deduplication logs provided dedupe is configured on the cluster nodes.
- *default*: This module collects logs from all modules of the cluster nodes except the *os* module.
- *all*: This module collects information for all the above modules from the cluster nodes.

Collecting time-based and archived logs

You can collect logs for a specific duration for the **sds** and **backup** modules.

Collecting logs for a specific duration reduces the time taken to collect and upload the logs to a remote server. You can also collect archived logs for all the modules.

The following command shows the options for collecting time-based and archived logs:

```
debuginfo upload nodename debug-URL module
archivedLogs={on|off|vxdefault} startDate endDate tarName
```

nodename Specifies the *nodename* from which to collect the debugging information.

debug-URL

Specifies the remote file or directory for uploading debugging information.

Depending on the type of server from which you upload debugging information, use one of the following example URL formats:

```
ftp://admin@ftp.docserver.company.com/  
patches/
```

```
scp://root@server.company.com:/tmp/
```

If *debug-URL* specifies a remote file, the debuginfo file is saved by that name. If *debug-URL* specifies a remote directory, the debuginfo file name displays as the following:

```
nas_debuginfo_nodename_modulename_timestamp.tar.gz
```

<i>module</i>	Specifies the values for <i>module</i>. The following options are supported: ■ <code>service-status</code>: Current status of services that are running in the cluster. ■ <code>performance</code>: Performance logs for the cluster nodes. ■ <code>common-logs</code>: Logs that are common across multiple modules for the cluster nodes. ■ <code>nas</code>: Product information from the cluster nodes. ■ <code>os</code>: Logs for kernel and user dumps. ■ <code>sos-report</code>: Uses RHEL utility to collect troubleshooting data for the operating system. The <code>sosreport</code> is collected for all the loaded modules except for the <code>selinux</code> module. ■ <code>explorer</code>: The VxExplorer utility collects logs and environment data from all the servers where the Access Appliance product is installed. ■ <code>install</code>: Install logs from the CPI install log directory <code>/opt/VRTS/install/logs/</code>. ■ <code>nas-procstacks</code>: Stack trace for all the daemons that are in running state. ■ <code>appliance</code>: Logs related to the appliance. ■ <code>sds</code>: SDS logs. ■ <code>upgrade</code>: Upgrade logs for all the cluster nodes. ■ <code>backup</code>: NetBackup client logs and other diagnostic information. ■ <code>vdd</code>: Deduplication logs provided Veritas Data Deduplication server is configured for the cluster. ■ <code>default</code>: Logs from <code>service-status</code>, <code>nas</code>, <code>explorer</code>, <code>install</code>, <code>nas-procstacks</code>, <code>appliance</code>, <code>sds</code>, <code>upgrade</code>, and <code>backup</code> modules of the cluster nodes. This is the default option. ■ <code>all</code>: This module collects information for all the above modules from the cluster nodes.
<code>archivedLogs</code>	Collects historical logs. Options are <code>on</code>, <code>off</code>, and <code>vxdefault</code>.
<code>startDate</code>	Start date in <code>mm/dd/yy</code> format if you want to collect logs for a specific duration. Time-based logs are collected only for <code>nas</code> and <code>sds</code> modules. Logs for <code>sds</code> and <code>nas</code> modules from the archived directory are also included.
<code>endDate</code>	End date in <code>mm/dd/yy</code> format if you want to collect logs for a specific duration. Time-based logs are collected only for <code>nas</code> and <code>sds</code> modules. Logs for <code>sds</code> and <code>nas</code> modules from the archived directory are also included.

tarName Name of the tar file that includes all the collected logs.

The following example shows how to upload all debug information to an FTP server including the archived logs:

```
Support> debuginfo upload node1_1  
ftp://admin@ftp.docserver.veritas.com/patches/ all archivedLogs=on
```

The following example shows how to upload all debug information to an FTP server excluding the archived logs:

```
Support> debuginfo upload node1_1  
ftp://admin@ftp.docserver.veritas.com/patches/ all archivedLogs=off
```

The following example shows how to upload all debug logs from all node for all modules for a specific duration. The logs for only **sds** and **backup** modules are collected for the specified duration; all logs are collected for all the other modules.

```
Support> debuginfo upload all file:///log/ all archivedLogs=off  
06/12/2023 06/25/2023
```

Collecting logs for cluster nodes

You can collect logs for an individual node in the cluster for error analysis and troubleshooting. You can choose to collect logs for all the components to get a comprehensive view of the system, or you can collect logs for specific components that have an issue.

To select logs individually

- 1 Login to <https://managementconsoleIP:14161/> using admin user credentials where *managementconsoleIP* is the management console IP address.
- 2 Go to **Settings > Diagnostics**.
- 3 Click **Generate log package**.
- 4 On the **Generate log package** page, select **Advanced** tab where you can select individual log files to include in the log package.
- 5 On the **Advanced** tab, under **Log settings**, expand the nodes and select the log files.
- 6 Under **Package options**, specify a name for the log package and optionally the case number if provided by Veritas Support.
- 7 Click **Generate**.

Monitoring Access Appliance

This chapter includes the following topics:

- [About monitoring Access Appliance operations](#)
- [Monitoring hardware components](#)

About monitoring Access Appliance operations

This chapter describes several support tasks that are useful for monitoring Access Appliance operations. Perform these monitoring tasks periodically to ensure that Access Appliance is running smoothly.

As you work with Access Appliance, keep an ongoing record of the output created by monitoring commands. This process gives you a baseline for judging normal operations and helps you to flag potential problems before they become serious.

Monitoring hardware components

Use the following commands to monitor the hardware components:

- `show hardware-health appliance component=`
Use this command to view the health of the hardware components and the primary and expansion shelves. The options for the component are **All/Product/Fan/Power/Temperature/CPU/Network/PCI/Firmware/Partition/RAID/Disk/DIMM/Certificate/CMOSBattery/DIMMPopulation/StorageStatus/Connection)[all]**
To view the health of the primary shelf, use the `show hardware-health primary-shelf component=` command. For example:

```
show hardware-health primary-shelf component=FAN
```

To view the health of the expansion shelf use the `show hardware-health expansion-shelf component= tray-id=` command where **tray-id** is the ID of the expansion shelf. For example:

```
show hardware-health expansion-shelf component=FAN tray-id=1
```

- `show hardware-errors`

Use this command to view the errors that are related to the hardware components.

Common recovery procedures

This chapter includes the following topics:

- [About common recovery procedures](#)
- [Restarting servers](#)
- [Restarting cluster services](#)
- [Bringing services online](#)
- [Recovering from a non-graceful shutdown](#)
- [Testing the network connectivity](#)
- [Troubleshooting with traceroute](#)
- [Using the traceroute command](#)
- [Collecting the metasave image of a file system](#)
- [Replacing an Ethernet interface card \(online mode\)](#)
- [Replacing an Access Appliance node](#)
- [Uninstalling a patch release or software upgrade](#)

About common recovery procedures

This chapter provides some of the most-common recovery procedures you can use to troubleshoot a problem with Access Appliance.

Restarting servers

Some configuration changes do not take effect until the associated server is restarted. Therefore, some configuration problems can be solved by stopping and restarting the associated server.

[Table 4-1](#) shows commands you can use to start and stop Access Appliance servers.

Table 4-1 Commands to start and stop servers

Command	Definition
Backup> start	Starts all configured backup services.
Backup> stop	Stops all configured backup services.
NFS> server start	Starts the NFS server.
NFS> server stop	Stops the NFS server.

Note: Some commands include the `server` argument and some do not. Also, some `Support>` commands use a `service` (instead of `server`) argument.

Restarting cluster services

There might be situations where you need to stop both the cluster nodes for maintenance tasks. When you stop both the cluster nodes, all the cluster services are stopped. You can stop each node individually by using the `cluster stop nodename` command, or you can stop both the cluster nodes using the `cluster stop all` command. When you stop both the nodes, either successively or simultaneously, all the cluster services are stopped and you don't have access to the command-line interface. To start the cluster services, you must use the following procedure.

To start the cluster services:

- 1 Use SSH to log on to one of the nodes using the admin credentials.
- 2 Elevate to root by using the `support elevate` command.
- 3 Run the following command to start the cluster services:

```
/opt/VRTSnas/scripts/cluster/cluster_config.sh start all
```

Bringing services online

The `Support> services` command lets you bring services that are OFFLINE or FAULTED back to the ONLINE state.

Note: After you use the `Support> services` command, if a service is still offline or faulted, you need to contact Technical Support.

These services include:

- Backup
- Console service
- FS manager
- GUI
- IP addresses
- NIC information
- NFS server

Using the services command

To display the state of the services

- ◆ To display the important services running on the nodes, enter the following:

```
Support> services show
```

	access	
Service	01	02
-----	-----	-----
nfs	ONLINE	ONLINE
gui	ONLINE	ONLINE
console	ONLINE	ONLINE
nic_pubeth0	ONLINE	ONLINE
nic_pubeth1	ONLINE	ONLINE
fs_manager	ONLINE	ONLINE

To display the state of all of the services

- ◆ To display all of the services running on the nodes, enter the following:

```
Support> services showall
```

	access	
Service	01	02
-----	-----	-----
nfs	ONLINE	ONLINE
console	ONLINE	ONLINE
gui	ONLINE	ONLINE
nic_pubeth0	ONLINE	ONLINE
nic_pubeth1	ONLINE	ONLINE
fs_manager	ONLINE	ONLINE
10.182.107.201	ONLINE	ONLINE
10.182.107.202	ONLINE	ONLINE
10.182.107.203	ONLINE	ONLINE
10.182.107.204	ONLINE	ONLINE
/vx/fs1	ONLINE	ONLINE

To fix any service fault

- ◆ To fix any service fault, enter the following:

```
Support> services autofix
Attempting to fix service faults.....done
```

To bring a service online

- ◆ To bring a service online on the nodes, enter the following:

```
Support> services online servicename
```

where *servicename* is the name of the service you want to bring online.

For example:

```
Support> services online 10.182.107.203
```

This IP address is the virtual IP address that can be onlined.

Recovering from a non-graceful shutdown

In some cases, when a non-graceful shutdown of a node occurs (for example, during an unexpected system halt or power failure), you may receive an error

message on the local node asking you to use the Linux `fsck` (file system check) command to repair files on the node.

To recover a node

- 1 Login to the Management console (Veritas command-line interface) prompt.
- 2 Run the following command:

```
storage>fs fsck <fsname>
```

where *fsname* is the name of the file system.

Once the file check is complete, you can continue to use the file system.

Testing the network connectivity

You can test whether a particular host or gateway is reachable across an IP network.

To use the ping command

- ◆ To use the ping command, enter the following:

```
Network> ping destination [nodename]  
[devicename] [packets]
```

For example, you can ping host1 using node1:

```
Network> ping host1 node1
```

<i>destination</i>	Specifies the host or gateway to send the information to. The destination field can contain either a DNS name or an IP address.
<i>nodename</i>	Specifies the <i>nodename</i> to ping from. To ping from any node, use <i>any</i> in the <i>nodename</i> field. The <i>nodename</i> field is an optional field. If <i>nodename</i> is omitted, any node is chosen to ping from.
<i>devicename</i>	Specifies the device through which you ping. To ping from any device in the cluster, use the <i>any</i> variable in the <i>devicename</i> field.
<i>packets</i>	Specifies the number of packets that should be sent to the destination. If the packets field is omitted, five packets are sent to the destination by default. The packets field must contain an unsigned integer.

Troubleshooting with traceroute

Traceroute is a widely-available utility supported by the Linux operating system. Much like ping, traceroute is a valuable tool to determine connectivity in a network. The Veritas Access `Support> ping` command enables you to discover connections between two systems. The `Support> traceroute` command checks system connections as well, but also lists the intermediate hosts between the two systems. Users can see the routes that packets can take from one system to another. Use the `Support > traceroute` command to find the route to a remote host. For example, you might use the `Support> traceroute` command to verify the connectivity of each node in your cluster.

Using the traceroute command

The `Support> traceroute` command displays all of the intermediate nodes on a route between two nodes.

To use the traceroute command

- ◆ To use the `Support> traceroute` command, enter the following:

```
Support> traceroute destination [source]
[maxttl]
```

<i>destination</i>	The target node. To display all of the intermediate nodes that are located between two nodes on a network, enter the <i>destination</i> node. You need to specify either an IPv4 address for an IPv4 installation or an IPv6 address for an IPv6 installation. The accepted range for an IPv6 prefix is 0-128 integers.
<i>source</i>	Specifies the <i>source</i> node name from where you want to begin the trace.
<i>maxttl</i>	Specifies the maximum number of hops. The default is seven hops.

For example, to trace the route to the network host, enter the following:

```
Support> traceroute www.veritas.com fssClus_01 10
traceroute to www.veritas.com (23.5.150.79), 10 hops max, 60 byte packets
 1 puna-sli-core-b01-vlan329.net.symantec.com (10.209.192.2) 0.356 ms 0.354 ms 0.376 ms
 2 punb-vfpi-eng-1-aggregate2-104.net.veritas.com (10.209.186.14) 0.298 ms 0.322 ms 0.379 ms
 3 puna-spi-core-b02-vlan105.net.symantec.com (143.127.185.130) 1.851 ms 1.964 ms 1.940 ms
 4 bnrcatcore01-teng6-2.net.symantec.com (143.127.185.205) 1.902 ms 1.903 ms 1.932 ms
 5 puna-vfpi-main-1-vip.net.veritas.com (10.212.252.50) 1.886 ms 1.945 ms 1.922 ms
```

Collecting the metasave image of a file system

You can collect a metasave image of a file system for troubleshooting file system issues. Metadata is a data structure that contains attributes about the data within a file system, but does not contain the actual data itself. You can use metadata images for tracking file system trends, such as the file size, age, and type of information in the file system.

Note: When using the `support metasave` command to create a consistent metasave image, if the file system is not offline on all the cluster nodes, a warning appears which has to be confirmed before you proceed. You can bring the file system offline using the `storage fs offline` command before collecting the metasave image. Metasave image collection is a time consuming operation. The total time that is required depends on the amount of metadata information present in the file system. You can run other Access Appliance operations from a separate terminal while running the metasave operation.

To collect the metasave image of a file system

- ◆ To use the `Support> metasave` command, enter the following:

```
Support> metasave [fsname] [output_location]
```

`fsname` Specifies the name of the file system for which you want to collect a metasave image of the file system.

`output_location` Specifies the directory location of the metasave image.

For a regular file system, a single metasave image is stored at the directory location specified by `output_location`.

For example, to collect the metasave image of file system `testfs`, and store it under `/tmp/meta_out_dir`, enter the following:

```
Support> metasave testfs /tmp/meta_out_dir
Collecting metasave image of file system testfs. This may take some time...
SUCCESS: Metasave image of testfs collected successfully.
Image is stored at /tmp/meta_out_dir.
```

Replacing an Ethernet interface card (online mode)

In some cases, you may need to replace an existing Ethernet interface card on a node. This section describes the steps to replace the NIC card. When you replace the NIC card, there should not be any mismatch with the number of NICs in the cluster. All the nodes in the cluster should have an equal number of disks after you replace the NIC card.

You need to provide an accurate and permanent MAC address (in case of bonded NICs) before you proceed with the NIC replacement. High availability services of service groups are temporarily disabled during the NIC replacement operation.

Note: This procedure does not work for adding an Ethernet interface card to the cluster and in VLAN environments. After the successful replacement operation, remove the faulty NIC card. Before you install the Ethernet interface card on the node, install the required device driver for the Ethernet interface card.

To replace an online Ethernet interface card (NIC)

- 1 Add a new NIC card on the server.

Note: The new NIC card should be online and searchable by the server.

- 2 Run the `# ip link show` command to get the MAC address of the new NIC card.
- 3 Run the following command on the Access Appliance node to replace the NIC card.

```
# /opt/VRTSnas/scripts/net/net_device_add.sh -r  
<old_mac_address> -w <new_mac_address>
```

- 4 To replace the NIC card in the bonded interface, you need to find a permanent hardware address by using one of the following commands.

```
# ethtool -P <interfacename>
```

or

```
# cat /proc/net/bonding/<bondname>
```

For details, see the following examples.

Example: To replace the "pubeth2" interface in the bond with the new NIC "eth0"

Bonding details:

```
# cat /proc/net/bonding/bond0  
Ethernet Channel Bonding Driver: v3.7.1 (April 27, 2011)
```

```
Bonding Mode: load balancing (round-robin)  
MII Status: up  
MII Polling Interval (ms): 100  
Up Delay (ms): 0  
Down Delay (ms): 0
```

```
Slave Interface: pubeth1
```

```
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 0
Permanent HW addr: 00:50:56:05:0a:ea
Slave queue ID: 0
```

```
Slave Interface: pubeth2
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 0
Permanent HW addr: 00:50:56:05:e0:45
Slave queue ID: 0
```

```
# ip link show
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT qlen 1
link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
2: priveth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP mode
DEFAULT qlen 1000
link/ether 00:50:56:05:a3:1d brd ff:ff:ff:ff:ff:ff
3: pubeth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq
state UP mode DEFAULT qlen 1000
link/ether 00:50:56:05:e0:44 brd ff:ff:ff:ff:ff:ff
4: pubeth1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500
qdisc mq master bond0 state UP mode DEFAULT qlen 1000
link/ether 00:50:56:05:0a:ea brd ff:ff:ff:ff:ff:ff
5: pubeth2: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500
qdisc mq master bond0 state UP mode DEFAULT qlen 1000
link/ether 00:50:56:05:0a:ea brd ff:ff:ff:ff:ff:ff
6: eth0: <BROADCAST,MULTICAST> mtu 1500 qdisc mq state DOWN mode DEFAULT qlen 1000
link/ether 00:50:56:05:41:53 brd ff:ff:ff:ff:ff:ff
7: priveth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP mode
DEFAULT qlen 1000
link/ether 00:50:56:05:e0:41 brd ff:ff:ff:ff:ff:ff
8: bond0: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc
noqueue state UP mode DEFAULT qlen 1000
link/ether 00:50:56:05:0a:ea brd ff:ff:ff:ff:ff:ff
```

NIC replacement operation

```
# /opt/VRTSnas/scripts/net/net_device_add.sh -r 00:50:56:05:e0:45
-w 00:50:56:05:41:53
100% [#] Success: Device replace successful.
```

After NIC replacement

```
# cat /proc/net/bonding/bond0
Ethernet Channel Bonding Driver: v3.7.1 (April 27, 2011)

Bonding Mode: load balancing (round-robin)
MII Status: up
MII Polling Interval (ms): 100
Up Delay (ms): 0
Down Delay (ms): 0

Slave Interface: pubeth1
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 0
Permanent HW addr: 00:50:56:05:0a:ea
Slave queue ID: 0

Slave Interface: pubeth2
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 0
Permanent HW addr: 00:50:56:05:41:53
Slave queue ID: 0
```

Replacing an Access Appliance node

In some cases, you may need to replace a Access Appliance node. This section describes the steps to replace a Access Appliance node.

It is not recommended to delete the node where the management console is running. however, if you want to delete this node, you should first switch the management console on to other node and then attempt to the delete node.

To switch the management console node:

- 1 Go to the Access command-line interface.
- 2 Run the `network ip addr show` command and note the console IP address.
- 3 Run the `network ip addr online console_ip target_node` command.

You will exit the Access command-line interface. You need to log in again.

To replace an Access Appliance node:

- 1 Before you delete the node from the cluster, make sure that you do not remove the CVM master node. To remove the CVM master node, you need to switch the CVM master node by switching the Management Console to another node.
- 2 Power-off the node to delete. Once the node is powered-off, run the `cluster del` command for the node that is to be replaced.

```
rvclus>cluster del node-name
```

- 3 Reimage the deleted node with the same ISO as before. Upgrade the node if required to bring the deleted node to the same version as the cluster node.
- 4 Run the `cluster add` command to add reimaged node to the cluster.

```
rvclus>cluster add node-ip
```

Uninstalling a patch release or software upgrade

Often a problem occurs because of a known product defect. Once the defect is fixed, you can install a patch release or software upgrade to fix the issue.

When you plan to install a patch release or software upgrade:

- Before you start the installation, use the `System> config export` command to save a copy of your configuration. After the upgrade, you can use the `System> config import` command to restore your configuration.

Example:

```
System> config export local 2016_July_20
```

```
System> config import local 2016_July_20 network
```

- To upgrade with minimal downtime, you need to obtain a set of temporary VIP and IP addresses to use during the upgrade. Alternatively, you can upgrade without using temporary VIP and IP addresses, but the downtime increases.

For details on upgrading Access Appliance, refer to the *Veritas Access Installation Guide*.

Troubleshooting Access Appliance installation and configuration issues

This chapter includes the following topics:

- [How to find the management console IP](#)
- [Viewing the installation logs](#)
- [Installation fails and does not complete](#)

How to find the management console IP

To find the management console IP:

- 1 Identify on which node the management console is running:

```
hastatus -sum | grep Management
```

The output displays the node on which the management console is online. The management console is online on only one of the nodes.

- 2 On the node where the management console is online, run the following command to get the IP address:

```
ifconfig -a eth1
```

- 3 To access the Access command-line interface, use Secure Shell (ssh) and connect to the management console IP with admin user credentials:

```
ssh admin@managementconsoleIP
```

- 4 To access the Access Appliance GUI, use the following URL:

```
https://managementconsoleIP:14161/
```

Viewing the installation logs

If a problem occurs during installation, it can be helpful to view entries in the installation logs to help pinpoint problems.

To view the Access Appliance installation logs

- 1 During Access Appliance installation and configuration, you can access installer logs in a temporary folder under `/var/tmp`.
- 2 After Access Appliance installation and configuration, you can view a copy of the installation logs in the following locations:

Access Appliance post-installation logs	<code>/opt/VRTS/install/logs/installaccess-<i>timestamp</i></code> This directory is located on the node from which the installer is triggered (the driver node). It contains the Access Appliance specific installation logs. For example: <code>/opt/VRTS/install/logs/installaccess-201602021544AsJ</code>
--	---

Access Appliance service group configuration logs	<code>/opt/VRTSnas/log/Install.log</code> This directory contains the Access Appliance specific configuration logs. For example: <code>/opt/VRTSnas/log/Install.log.201407030655</code>
---	---

Access Appliance network installation and configuration logs	<code>/opt/VRTSnas/log/install_network.log</code> This directory contains the Access Appliance network configuration logs. For example: <code>/opt/VRTSnas/log/install_network.log.201407030655</code>
---	--

Installation fails and does not complete

Some common reasons for installation failures include:

- Gateway access
The Access Appliance node must be able to reach the default gateway using the public network. Verify with your network administrator that the gateway is reachable.

Troubleshooting Access Appliance GUI startup issues

This chapter includes the following topics:

- [Resolving GUI startup issues](#)

Resolving GUI startup issues

Access Appliance GUI accessibility issues occur if specific ports are inaccessible. Ports might be turned off on the node or on the network switch. Veritas selectively opens ports at the network switch.

To use the Access Appliance GUI after installing Access Appliance

- 1 Obtain the console virtual IP address by using the `network ip addr show` command.
- 2 Use the console IP with the port number 14161 to access the Access Appliance GUI.

Example:

```
https://console IP address:14161
```

- 3 Log on to the Access Appliance GUI using the `admin` user name and password.
If this does not work, verify the GUI set up.

To verify the GUI set up

- 1 Check the `/opt/VRTSnas/log/isagui_config.log` file to verify that the GUI is properly configured.

If there are any problems during the configuration, the problems are reported in this log file.

- 2 You need to allow ports 5634 and 14161 to be accessible remotely.
- 3 Open these ports by executing the following commands.

You must log on as the `root` user.

```
# /etc/init.d/iptables save
# /etc/init.d/iptables stop
```

- 4 Turn off the firewall on start up:

```
# chkconfig firewalld off
```

The commands work if there is no network switch-based firewall in the environment. Otherwise you need to contact the network administrator to open these ports.

- 5 Ports must be opened before the GUI is configured. Otherwise you should rerun the GUI configuration. Before you rerun the GUI configuration, try connecting the browser to the management console.

- 6 You can verify if a port is accessible by running the following command:

```
telnet hostname/ipaddress 14161
```

If the port is not opened or not listened to, the connection waits forever. Try connecting with a random port that is not open. You see a difference in behavior.

- 7 Restart if the web server is not running.

```
# /opt/VRTSnas/pysnas/bin/vamgmt -h
# /opt/VRTSnas/pysnas/bin/vamgmt status

# ps -ef | grep node
```

After running the `ps -ef | grep node` command, the results should show:

```
/opt/VRTSnas/isagui/ext_modules/node /opt/VRTSnas/isagui/application/server.js production
```

- 8 You should be able to connect to the GUI and be able to log on.

- 9** If data is not properly discovered or not seen in the GUI, run the following commands:

```
export EXTRA_LOG=1
```

```
/opt/VRTSnas/pysnas/bin/isagui_cluster_perf.py --full
```

- 10** If there are any errors, check the log file.

```
/opt/VRTSnas/log/isagui_cluster_perf.log
```

Troubleshooting Veritas Data Deduplication issues

This chapter includes the following topics:

- [Log locations for the Veritas Data Deduplication server](#)

Log locations for the Veritas Data Deduplication server

If the VDD server goes into unhealthy state, you can check the HA log files for the reason of failure.

- `/log/VRTSnas/log/vacontainersha_monitor.log`
- `/log/VRTSnas/log/msdpwormha_monitor_<config_name>.log`

The log files for the operations that are performed on the Veritas Data Deduplication server are present in the following format:

`/log/VRTSnas/log/dedupe_<operation>.log`

Index

A

- a node
 - replacing 31
- about
 - common recovery procedures 21
 - event logs 10
 - monitoring commands 19
 - services command 23
- Access Appliance log files
 - viewing 8
- an Ethernet interface card (online mode)
 - replacing 28

C

- common recovery procedures
 - about 21

D

- debugging information
 - retrieving and sending 11
- debugging options
 - setting for NetBackup 10

E

- event logs
 - about 10

G

- general techniques
 - troubleshooting 7
- general tips
 - troubleshooting process 6

I

- installation
 - common failures 35
- installation logs
 - viewing 34

M

- monitoring
 - installation logs 34
- monitoring commands
 - about 19

N

- NetBackup client log levels
 - setting 10
- NetBackup debugging options
 - setting 10
- network
 - testing connectivity 25

P

- patch release
 - uninstalling 32

R

- recovering
 - from a non-graceful shutdown 24
- replacing
 - a node 31
 - an Ethernet interface card (online mode) 28
- restarting
 - servers 22
- retrieving
 - debugging information 11

S

- sending
 - debugging information 11
- servers
 - restarting 22
- services command
 - about 23
 - using 23
- setting
 - NetBackup client log levels 10

- shutdown
 - recovering from a non-graceful 24
- software upgrade
 - uninstalling 32

T

- testing
 - network connectivity 25
- traceroute
 - troubleshooting with 26
- traceroute command
 - using 26
- troubleshooting
 - about 6
 - general procedures 8
- troubleshooting process
 - general techniques 7
 - general tips 6

U

- uninstalling
 - patch release or software upgrade 32
- using
 - services command 23
 - traceroute command 26

V

- viewing
 - Access Appliance log files 8
 - installation logs 34